MobileSDR:

A Mobile Programmable Platform for Wireless Field Tests and Diagnostics

AIMS-2025

Zesen Zhang, Rohith Reddy Vennam, Maiyun Zhang, Yunxiang Chi, Dinesh Bharadia, Aaron Schulman







Infrastructure Components in Access Network







What is wireless measurement


Using sensors to collect analog signal and process with program to capture key information in the signal

- Sensors: Collect raw data, such as sound, FM, LoRa, cellular signal
- Analog-to-digital converter: Converts the raw data to a digital format if needed.
- Key feature capture: FFT, demodulation.
- Further analysis: Packet decoding, decryption...

What is SDR



 Software-defined radio (SDR) is a radio communication system who uses software to implement components which is conventionally implemented by analog hardware.



Collecting Wireless Data in the field is not easy...








Bring a laptop with SDR and Drive/Walk around to collect data

What if...



Connect SDR to laptop





Connect SDR to Phone

So that...










Bring a phone with SDR and Drive/Walk around to collect data

What if...




MobileSDR Goal

Separate wireless data collection from program design

Developing a crowdsourced platform

- Researchers design programs in the lab and publish them on the platform
- Users download tasks to their phones and gather data via SDR
- Users then upload the collected data to the platform, making it available for everyone

MobileSDR architecture



Easy for endpoints to collect data and join the ecosystem

Ensure program security running on endpoint's device

Ensure data integrity

Save battery on the phone

Easy for endpoints to collect data and join the ecosystem

Ensure program security running on endpoint's device


Ensure data integrity

Save battery on the phone

Ensure program security running on endpoint

Use domain specific language to restrict what researchers can run on the platform while providing enough flexibility

A domain-specific language (DSL) is a computer language specialized to a particular application domain.



Only allow sending XML file instead of binary



```
options:
  parameters:
    author: ''
    category: '[GRC Hier Blocks]'
    cmake opt:
    comment: ''
    copyright: ''
    description: ''
    den cmake: 'On'
    gen linking: dynamic
    generate_options: no_gui
    hier block src path: '.:'
    id: androidsdrtest
    max nouts: '0'
    output language: python
    placement: (0,0)
    qt qss theme: ''
    realtime scheduling: ''
    run: 'True'
    run_command: '{python} -u {filename}'
    run options: run
    sizing mode: fixed
    thread safe setters: ''
    title: Not titled vet
    window size: (1000,1000)
  states:
    bus sink: false
    bus source: false
    bus structure: null
    coordinate: [8, 8]
    rotation: 0
    state: enabled
blocks:
  name: samp rate
  id: variable
```




Mako template

```
if python version == 2:
rom __future__ import print_function
if generate_options == 'qt_gui':
rom distutils.version import StrictVersion
  _name__ == '__main__':
  import ctypes
  import sys
  if sys.platform.startswith('linux'):
        x11 = ctypes.cdll.LoadLibrary('libX11.so')
        x11.XInitThreads()
        print("Warning: failed to XInitThreads()")
for imp in imports:
##${imp.replace("  # grc-generated hier_block", "")}
endfor
Write the class declaration for a top or hier block.
  The parameter names are the arguments to init .
```




```
!/usr/bin/env python3
 -*- coding: utf-8 -*-
 SPDX-License-Identifier: GPL-3.0
 GNU Radio Python Flow Graph
 Title: Not titled vet
 GNU Radio version: v3.8.5.0-6-q57bd109d
 om gnuradio import blocks
  om gnuradio import gr
  om gnuradio.filter import firdes
  port sys
 port signal
  om argparse import ArgumentParser
   gnuradio.eng_arg import eng float, intx
 om gnuradio import eng_notation
 om gnuradio import uhd
 nport time
class androidsdrtest(gr.top_block):
   def __init__(self):
      gr.top block. init (self, "Not titled yet")
      # Variables
      **************************************
      self.samp rate = samp rate = 30720000
      ***********************************
      # Blocks
      self.uhd usrp source tofile 0 = uhd.usrp source tofile(
```

Architecture on the endpoint side



Access control



Easy for endpoints to collect data and join the ecosystem


Ensure program security running on endpoint's device

Ensure data integrity

Save battery on the phone

Broker automatically sign tasks to endpoint

Broker in the middle control task assignment



Configuration file

```
"centerlat": "32.86180629",
    "centerlong": "-117.21663798",
    "StartTime": "12333333444",
    "ExpTime": "-1",
    "range": "1000",
    "DuplicateTime": "1"
```



SDR Name: USRP B200

Latitude: 32.86171285

Longitude: -117.21669952

Last Update Time: 2024-10-29T07:04:16Z

Experiment configuration

Endpoint configuration

Metadata

```
"annotations": [
        "core:freq_lower_edge": 731319999.9987841,
        "core:freq_upper_edge": 746680000.0107517,
        "core:sample_count": 5000000
"captures": [
        "core:datetime": "1, 0.250172",
        "core:frequency": 739000000.0047679
"global": {
    "core:datatype": "cf32_le",
    "core:hw": "USRP B200",
    "core:sample_rate": 15360000.011967678,
    "core:version": "v0.0.2"
```

MobileSDR demo with MIB/SIB decoder



Thanks for your attention

Easy for endpoints to collect data and join the ecosystem

Ensure program security running on endpoint's device

Ensure data integrity

Save battery on the phone

Easy for endpoints to collect data

Allow SDR connected with portable devices (Android phone) to collect data

Cross compile SDR's framework on the phone

1. Cross compile with Android

2. Compile on Termux:
environment on Linux:

```
### CONFIG
export TOOLCHAIN ROOT=${HOME}/Android/Sdk/ndk/21.3.6528147
export HOST_ARCH=linux-x86_64
### DERIVED CONFIG
export SYS_R00T=${T00LCHAIN_R00T}/sysroot
export TOOLCHAIN_BIN=${TOOLCHAIN_ROOT}/toolchains/llvm/prebuilt/${HOST_ARCH}/bin
export API_LEVEL=29
export CC="${TOOLCHAIN_BIN}/aarch64-linux-android${API_LEVEL}-clang"
export CXX="${T00LCHAIN BIN}/aarch64-linux-android${API LEVEL}-clang++"
export LD=${TOOLCHAIN_BIN}/aarch64-linux-android-ld
export AR=${TOOLCHAIN BIN}/aarch64-linux-android-ar
export RANLIB=${TOOLCHAIN_BIN}/aarch64-linux-android-ranlib
export STRIP=${TOOLCHAIN_BIN}/aarch64-linux-android-strip
export BUILD ROOT=$(dirname $(readlink -f "$0"))
export PATH=${TOOLCHAIN_BIN}:${PATH}
export PREFIX=${BUILD_ROOT}/toolchain/arm64-v8a
export PKG_CONFIG_PATH=${PREFIX}/lib/pkgconfig
export NCORES=$(getconf _NPROCESSORS_ONLN)
```

```
1:54 🗭 👸 🕅 🖠 🏃
                                     64/" (ignoring)
  /com.termux/files $ cd home
  $ termux-usb -1
  $ termux-usb -1
  "/dev/bus/usb/001/002"
   termux-usb -r /dev/bus/usb/001/002
  $ termux-usb -r /dev/bus/usb/001/002
Access granted.
  $ termux-usb -e "./iio info -S usb=0456:b673" /dev/bus
Tracking... iio_scan_context_get_info_list_android
Tracking... usb_context_scan_android
        0: 0456:b673 (Analog Devices Inc. PlutoSDR (ADAL
M-PLUTO)), serial=1044730a1997000a05002700013f7ba113 [us
 $ termux-usb -e "./iio info -S usb" /dev/bus/usb/001/0
Tracking... iio_scan_context_get_info_list_android
Tracking... usb_context_scan_android
Available contexts:
        0: 0456:b673 (Analog Devices Inc. PlutoSDR (ADAL
M-PLUTO)), serial=1044730a1997000a05002700013f7ba113 [us
```


Easy for endpoints to collect data and join the ecosystem

Ensure program security running on endpoint's device

Ensure data integrity

Save battery on the phone

Duty Cycle




Easy for endpoints to collect data and join the ecosystem

Ensure program security running on endpoint's device


Ensure data integrity

Save battery on the phone

Go through computation limitation on the phone



Load tasks on different devices



Load tasks on different devices

